

UDS Enterprise 4.0 Graphic Customization





Index

ntroducción	2
JDS administration panel	2
CSS field	3
Identify the parameter to modify	3
Examples of modification of the "CSS" field	5
Field "Logo Name"	24
Field "Show Filter on Top"	25
Field "Site copyright info"	26
"Site copyright link" field	27
"Site information" field	28
Field "Site name"	29
Aodify browser tab	30
Change the image	30
Modify the text	31
JDS Enterprise Update	32
JDS ENTERPRISE, THE SOFTWARE VDI OF VIRTUAL CABLE	33
About UDS Enterprise	33
About Virtual Cable	33

Introducción

VIRTUAL CABLE

UDS Enterprise allows its customization to provide the tool with the corporate appearance necessary for each client. We can modify the different access sections related to users, the login portal as well as the download sections for actors and clients.

It will not be possible to customize any section of the UDS Enterprise administration.

Customization is done quickly and easily from the software's administration panel itself, with specific fields for some sections and the use of HTML5 tags and language.

UDS administration panel

In this section we are going to explain some of the possible modifications that can be made from the UDS Enterprise Dashboard. In order to carry out these customizations we must carry out the following actions:

- Access UDS Enterprise with a user with administrator permissions.
- Enter the UDS Enterprise Dashboard.
- In the side menu we will go to "Tools\Settings".
- We will click the Custom Tab "Custom Tab"

\$	O Configuración UDS				
🛄 Summary	UDS	Security	Admin	Custom	Other
⊆ Services ▼		css			
Authentication $\overline{}$					
Cs Managers		UDS Enterprise D	emo Online		
😳 Connectivity 🗸		Min. Services to show	filter		
Pools -		Show Eiltor on T	ten (
🖶 Tools 🗸		Site copyright info	S.L.U.		
Gallery		- Site copyright link			
🗋 Reports		https://www.uds	enterprise.com/en		
Notifiers		- Site information			<u>*</u>
🗄 Tokens 🗸		<pr><pr>d</pr></pr>			The second secon
Oonfiguration		Access to UDS 0	Inline Demo		
🗍 Flush Cache					

CSS field

VIRTUAL CABLE

In this field we are going to add the visual modifications that we need to make in the login portal and user services through "css" tags. After completing the configuration, we will click on the "**save**" button to apply the changes made.

UDS	Security	Admin	Custom	Other
	_ CSS			- 7
	UDS Enterprise Der	mo Online		
	Min. Services to show filt 8	ler		
	Show Filter on Top Site copyright info Virtual Cable S.L	.U.		
	Site copyright link	terprise.com/en		
	Site information			in in iteration
	Site name Access to UDS Onli	ine Demo		
		Save		

We must press F5 or refresh the page to see the result of the change.

Identify the parameter to modify

In this section we are going to explain how to identify the necessary labels to be able to make the modification from the UDS Enterprise administration. For this we will need to rely on a browser, for example: Mozilla Firefox.

After opening the browser with the URL of our UDS Server, we will press the right button, and in the drop-down menu we will select "**Inspect element**":

	← → ୯ ☆	
	Guar <u>d</u> ar como Guardar página en Poc <u>k</u> et	
	En <u>v</u> iar página al dispositivo	>
	Ver imagen de <u>f</u> ondo Seleccion <u>a</u> r todo	
	⊻er código fuente de la página Ver información de la página	
	Inspeccionar propiedades de accesibilidad	
	Inspeccionar elemento	
8	Hacer una captura de pantalla	

At the bottom of the browser will open the content of the web page. We can identify the section and the element that we want to modify by clicking on the different sections, such as identifying the login image:



Once we have identified the field we want to modify, we can go to the UDS Enterprise administration and make the change we need.

Next, we show various customization examples that you can rely on to make your own configuration.

Examples of modification of the "CSS" field

Change the icon on the top left

VIRTUAL CABLE



To make the modification of this section of the web we must enter the label "udsicon" in the "css" field. With HTML code we will indicate the size, the area in which we want to apply the change and where the image is located. Example:

.logo img{
width:80px;
height:50px;
<pre>box-sizing:border-box;</pre>
<pre>padding-left:80px;</pre>
background: url('https://udsenterprise.com/wp-content/uploads/2023/05/img-
<pre>logotipo-top-00-udsenterprise.jpg') left top no-repeat;</pre>
<pre>background-size: 80px 50px;}</pre>

Security	Admin	Custom
- CSS		
.logo img{		
width:80px;		
height:50px;		
box-sizing:border-box;		
padding-left:80px;		
background: url('https://udsenterprise	com/wp-content/uploads/2023/05/img-lo	gotipo-top-00-udsenterprise.jpg')
left top no-repeat;		
background-size: 80px 50px;}		
		11



Remove icon from top left

(IRTUAL CABLE

This section details how to remove the icon from the top bar of the access page to UDS Enterprise:

			生 UDS Client	i About	√ English
		UDS Enterprise			
	Username*				

We will introduce the following code in the CSS section of the configuration:

```
button[routerlink="/"] {
```

```
display: none;
```

}

Security	Admin	Custom
CSS button[routerlink="/"] { display: none; }		

Once the code is entered, this is the result:



Remove the "about" link from the top bar

CIRTUAL

This section shows how to remove the "**about**" link from the access page to UDS Enterprise:



In the CSS section of the UDS Enterprise configuration we will insert the following code:

The result after adding the code:

Remove the download link of the UDS Client

VIRTUAL CABLE

This section explains how to remove the UDS Client download link from the UDS Enterprise home page:

	🛃 UDS Client	i About	← English
UDS Enterprise			

In the CSS section of the UDS Enterprise configuration we will insert the following code:

```
button[routerlink="/client-download"] {
```

```
display: none;
}

Security Admin Custom

Custom
```

The result after the modification would be:

Add links in the top bar

CABLE

In this section, we are going to detail the tasks to be carried out to add one or more links at the top of the user area.

UDS		🛨 UDS Client	i About	→ English
	UDS Enterprise			
	Username*			
	Password			

In order to add links to the top bar of the home page, we must enter the UDS Server (Using WinSCP or similar software) and access the index.html file in the path /var/server/uds/templates/uds/modern /index.html and in the line where it says <body> we will replace it with the following code:

```
<script type="text/javascript">
function updateLinks() {
  try {
    var placeholder = document.getElementsByTagName('uds-
navbar')[0].getElementsByTagName('button')[1];
    placeholder.insertAdjacentHTML('afterend', '<a class="mdc-
button_label mat-focus-indicator mat-button mat-button-
base" href="https://www.udsenterprise.com/">Link Text</a>');
  } catch(error) {
    setTimeout(updateLinks, 400);
  }
}
```

NOTE: When copying the code, it is possible that its format is not correct depending on the browser and application used. In the following screenshot you will see the necessary format for its correct operation:

Here is the change:

/IRTUAL

```
/var/server/uds/templates/uds/modern/index.html - root@192.168.0.6 - Editor - WinSCP
🖬 🔓 2 🖣 🐇 💼 🗙 a 🍤 🥙
                                🛗 🌺 🛗 🔚 🛛 Encoding 🕶 🗔 Color 🕶 🎲 📿
<body>
  <uds-root>
      <!-- loading layout replaced by app after startupp -->
      <div class="app-loading">
        <div class="logo"></div>
        <svg class="spinner" viewBox="25 25 50 50">
          <circle class="path" cx="50" cy="50" r="20" fill="none" strol
        </svg>
/var/server/uds/templates/uds/modern/index.html - root@192.168.0.6 - Editor - WinSCP
🔚 🔄 🖻 👘 🐇 💼 🗶 🕘 🍤 🥙 🏙 🎭 🗟 🖷 🛛 Encoding 🕶 🗆 Color 🕶 🎆
  <script type="text/javascript">
  function updateLinks() {
   try {
      var placeholder = document.getElementsByTagName('uds-navbar')[0].ge
      placeholder.insertAdjacentHTML('afterend', '<a class="mat-focus-ind:
      // Repeat previous line to create more links...
    } catch(error) {
      setTimeout(updateLinks, 400); // Retry later
    }
  }
  </script>
<body onload="updateLinks();">
```

We will modify the code href="<u>http://www.udsenterprise.com</u>" replacing it with the URL to which we want the link to go.

To modify the text that will appear as a link, we will modify the text "Link text", by which we want it to appear.

This is the result of the modification:

VIRTUAL **CABLE**

UDS	🛨 UDS Client Link Text 👔 About 👻 English
	UDS Enterprise
	Username*
	Password

If we want to add another additional link, we will add the following line of code (with the link and text changed to the desired ones):

placeholder.insertAdjacentHTML('afterend', ' <a <="" class="mat-focus-indicat</th><th>or mat-</th></tr><tr><th>button mat-button-base" th=""><th></th>	
<pre>href="http://www.udsenterprise.com">Link text');</pre>	
🕼 /var/server/uds/templates/uds/modern/index.html - root@192.168.0.6 - Editor - WinSCP - 🗆 🗙	
🕞 😋 😰 🐘 余 🏥 🗶 副 🎐 C 🕌 歳 蒜 📾 [Encoding • □ Color • }]] 🕜	
<pre>cscript type="text/javascript"> function updateLinks() { try { var placeholder = document.getElementsByTagName('uds-navbar')[0].getElementsByTagName('button')[1]; placeholder.insertAdjacentHTML('afterend', 'ta class="mat-focus-indicator mat-button-base" href="http://www.udsenterprise.com">Link text'); placeholder.insertAdjacentHTML('afterend', 'ta class="mat-focus-indicator mat-button-base" href="http://www.udsenterprise.com">Link text'); placeholder.insertAdjacentHTML('afterend', 'ta class="mat-focus-indicator mat-button-base" href="http://www.demo.udsenterprise.com">Link text'); // Kepeat previous line to create more links / catch(error) { setTimeout(updateLinks, 400); // Retry later } // cscript codo nload="updateLinks();"> // Kepeat previous link ('store links) codo nload="updateLinks();"> // Kepeat previous link ('store links) catch(error) { setTimeout(updateLinks();") // Retry later } // compared links('store links');"> // Retry later // setTimeout(updateLinks();") // Retry links('store links');") // Retry links('store links');"> // Retry links('store links');") // compared links('store links');") //</pre>	

Change the login screen logo

	UDS Enterprise	
Username *		
Password		

To modify this section of the website, we must enter the label "login-brand img" in the "css" field. With HTML code we will indicate the size, the area in which we want to apply the change and where the image is located. Example:

```
.login-brand img {
width:96px;
height:96px;
box-sizing: border-box;
padding-left:96px;
background:url('https://www.udsenterprise.com/static/img/test.png')
left top no-repeat;
background-size: 96px 96px;
}
```

_ CSS		1
.login-brand img {		
width:96px;		
height:96px;		
box-sizing:border-box;		
padding-left:96px;		
background:url('https://udsenterprise.com/wp-content/uploads/2023/04/img-015-seguridad-		
udsenterprise.jpg')		
left top no-repeat;		
background-size: 96px 96px;	_	
}	1	

After applying the modification, the result would be the following:

	UDS Enterprise	
Username*		
Password		
	Login	

Change the color of the top bar and the text in the login portal

To modify this section of the website, we must enter the label "mat-toolbar.mat-primary" in the "css" field. With HTML code we will indicate the area where we want to apply the change and the color we want to use. Example:

.uds-nav {				
ł	<pre>background: #646e01 !important;</pre>			
¢	color: #000;			
}				
	Security	Admin	Custom	

Change the background color of the portal

	UDS Enterprise	
Username *		
Password		
	Login	

To modify this section of the website, we must enter the "background" label in the "css" field. With HTML code we will indicate the color that we want to use. Example:

body, html {			
background	: #73ff59;		
}			
	Security	Admin	Custom
	CSS body, html { background: #73ff59; }		

	🛨 UDS Client	i About 👻
UDS Enterpr	ise	
llsername*		
osemane		
Descured		
Password		
Login		

Change the size of the top bar

VIRTUAL **CABLE**

UDS UDS Lient i About English 🗸	
---------------------------------	--

To modify the size of this section of the web, in the event that the image used is larger than the size of the bar, we must enter the label "**mat-toolbar-row.mat-toolbar**" in the "css" field -single-row". With HTML code we will indicate the size of the bar. Example:

```
.mat-toolbar-row, .mat-toolbar-single-row {
    height: 128px !important;
}

Security Admin Custom

Custom

Custom

Custom

.mat-toolbar-row,.mat-toolbar-single-row {
    height: 128px !important;
    }
```

UDS		🛨 UDS Client	i) About	🗕 English
	UDS Enterprise			
	Username*			
	Password			

Change the position of the logo and the login screen form

VIRTUAL CABLE

	UDS Enterprise	
Username *		_
Password		_
	Login	

If we have modified the size of the top bar, we must change the position of both the logo and the login screen form. To modify the positioning of the login image, in the event that the top bar overlaps, we must enter the "**login-brand**" label in the "**css**" field. With HTML code we will indicate the position where we want to place it. Example:

.login-brand { padding: 1rem 0 0; } Security Admin Custom CSS .login-brand { padding: 1rem 0 0; }

After applying the modification, the result would be the following:

To modify the positioning of the login form, in the event that the top bar overlaps, we must enter the "**content**" label in the "**css**" field. With HTML code we will indicate the font size. Example:

. co	ntent {		
	<pre>margin: 5rem auto 0 !important;</pre>		
}			
	Security	Admin	Custom
	- CSS		
	.content { margin: 5rem auto 0 !imp	ortant;	
	}		

K	
UDS Er	terprise
Username *	
Password	
Log	In

© Virtual Cable S.L.U.

Change the positioning of the name of the software development company

VIRTUAL CABLE

To modify the positioning of the name of the software development company, we must enter the "**footer**" label in the "**css**" field. With HTML code we will indicate the position where we want to place it within the footer. Example:

foot	ter {		
ź	justify-content: ce	enter !important;	
r			
	Security	Admin	Custom
	Security	Admin	Custom
	Security - CSS .footer { justify-content: center !imp	Admin	Custom

© Virtual Cable S.L.U.

Insert text in the login portal

	UDS Enterprise	
Username *		
Password		
	Login	

To add text below the login portal form, we must enter the label "**login-container::after**" in the "css" field. With HTML code we will indicate the position where we want to place it within the footer. Example:

.login-container::after { content: 'To change your password, go to https://192.168.11.179'; } Security Admin Custom Cus

After applying the modification, the result would be the following:

Password		
	Login	

To change your password, go to https://192.168.11.179

Insert text in user services page

Windows Desktops					^
Console - Demo	Veyon teacher	Win10	Win7	Win2019	
釐 APPs					~

To add text to the user services page, we must enter the tag "**services-groups::after**" in the "css" field. Example:

.s	ervices-c	roup	::after {	
}	content:	' T o	change your password, go to https	://192.168.11.179';
	Se	curity	Admin	Custom
	servic	es-group	s::after {	

After applying the modification, the result would be the following:

Seneral General	~
Windows Virtual Desktops	~
Windows Virtual Apps	~
👌 Linux Virtual Desktops	~
Einux Apps	~
Remote access to physical devices	~
To change your password, go to https://192.168.11.179	

NOTE: This text will be visible to all users.

Insert text in the information panel

	Information	
IPs	Client IP	~
Transports	UDS transports for this client	~
Networks	UDS networks for this IP	~

To add text to the user services page, we must enter the tag "**staff-info::after**" in the "css" field. Example:

.staff-i	nfo::after {			
content:	'To change yo	r password, go to https://	192.168.11.179';	
}				
	Security	Admin	Custom	ĺ
.s }	taff-info::after { content: 'To change your pa	ssword, go to https://192.168.11.179';		

After applying the modification, the result would be the following:

	Information	
IPs	Client IP	
Transports	UDS transports for this client	```
Networks	UDS networks for this IP	

NOTE: This text will be visible only to administrator users and organization staff.

Change the font size of the user services header

Modifying the font size of the services header is done by entering the "**services-group-title**" tag in the "css" field. With HTML code we will indicate the font size of the text, in "px" or "em". In the following example we have used the size in pixels:

VIRTUAL **CABLE**

After applying the modification, the result would be the following:

General
Windows Virtual
Desktops

NOTE: This change will be visible to all users.

Change the size of the user services header

VIRTUAL **CABLE**

We can modify the size of the header of the user services by introducing the label "**mat-expansion-panel-header-title**" in the "css" field. With HTML code we will indicate the size of the bar that we want to use by percentage. Example:

After applying the modification, the result would be the following:

NOTE:This change will be visible to all users.

Field "Logo Name"

VDS Enterprise Demo Online

The "**Logo Name**" field allows us to modify the name that appears next to the image located in the upper left corner. In this example we are going to modify it by the UDS Enterprise text string.

Security	Admin	Custom	
- CSS		©,	
UDS Enterprise			
Logout URL			
Min. Services to show filter 8			

For this modification to be applied, we must press the "save" button and restart the Appliance UDS Server (or the "udsweb" service).

Field "Show Filter on Top"

VIRTUAL CABLE

The "Show Filter on Top" field allows us to add a search field in the user services panel, so that you can search within the services that are available to you.

Show Filter on Top			
yes			
Site copyright info			
© Virtual Cable S.L.U.			

By enabling this option, we will allow the "**filter**" field to appear in the upper right corner of the "**resources**" window. It will be visible to all users.

For this modification to be applied, we must click on the "**save**" button and restart the Appliance UDS Server (or the "**udsweb**" service).

					Filter	
👩 Windov	vs Desktops					^
Console - Demo	UDS Veyon teacher	Win10	₩in7	Win2019		
APPs						
Formacion						
👌 Linux Desktops						

© Virtual Cable S.L.U.

Test

Field "Site copyright info"

VIRTUAL CABLE

The "**Site copyright info**" field allows us to modify the text that appears in the lower right corner. In this example we will use the text string Test:

Site copyright info			
Test			
Site copyright link			
https://www.udsenterprise.	com		

For this modification to be applied, we must click on the "**save**" button and restart the Appliance UDS Server (or the "**udsweb**" service).

"Site copyright link" field

VIRTUAL CABLE

In this field it is possible to modify the URL of the hyperlink to which the text string that we have entered in the "**Site copyright info**" field refers to. To make this modification we must modify the parameter "**Site copyright link**". Example:

Site copyright link	
www.google.es	
Site information	
	//

With this change, clicking on the text will open the URL <u>www.google.es</u>. For this modification to be applied, we must click on the "save" button and restart the Appliance UDS Server (or the "**udsweb**" service).

"Site information" field

VIRTUAL CABLE

In this field you can enter the text that you want to appear under the UDS Enterprise login window (it supports HTML code).

In this example we are going to use the text string. Please enter your credentials:

Site information Please enter your credentials	
	//
Site name	
UDS Enterprise	

For this modification to be applied, we must click on the "save" button and restart the Appliance UDS Server (or the "udsweb" service).

This is the result of the modification:

Username *		UDS Enterprise	
Username * Password Login		UDS Enterprise	
Password	Username *		
Login	Password		
Login			
		Login	

Please enter your credentials

Field "Site name"

VIRTUAL CABLE

	UDS Enterprise	
Username *		_
Password		
	Login	

The "**Site name**" field allows us to modify the text that is located under the logo in the login window.

To make the modification we must place ourselves in the "**Site name**" field and indicate the text that we want to be visible to users. Example:

Site information	
Site name	
UDS Enterprise Demo	

For this modification to be applied, we must click on the "**save**" button and restart the Appliance UDS Server (or the "**udsweb**" service).

UDS Enterprise Demo	
Email	
Password	
Login	

Modify browser tab

IRTUAL

In this section we are going to detail the tasks to be carried out to modify the information that appears in the browser tab when connecting to the front of UDS Server.

Change the image

In order to change the icon that appears in the browser tab, we must connect to the UDS Server (via WinSCP or similar software) and access the path where the image is stored **/var/server/static/modern/img/:**

		-		
🗄 📄 Download 🔹 📝 Edit 🔹 🗙 🛃 🕞 Properties	🚰 New 🔹 🕂 📃 🗑			
/var/server/static/modern/img/				
Name	Size	Rights	Owner	Changed
e		rwxr-x	uds	22/04/2021 12:00:31
favicon.ico	4 KB	rw-r	uds	22/04/2021 12:00:31
i favicon.png	3 KB	rw-r	uds	22/04/2021 12:00:31
Linux.png	21 KB	rw-f	uds	22/04/2021 12:00:31
🖻 login-img.png	6 KB	rw-r	uds	22/04/2021 12:00:31
MacOS.png	11 KB	rw-r	uds	22/04/2021 12:00:31
🛋 udsicon.png	7 KB	rw-r	uds	22/04/2021 12:00:31
Windows.png	2 KB	rw-r	uds	22/04/2021 12:00:31

After finding ourselves in the path where the image is, we will replace the **favicon.png** file with the new one that we want to use. After this modification, we must restart the Appliance UDS Server for the change to be applied.

NOTE: This modification must be carried out in all the UDS Servers that we have deployed.

Modify the text

IRTUAL

In order to modify the text that appears in the browser tab, we must access the UDS Server (using WinSCP or similar software) and go to the path /var/server/uds/templates/uds/modern/.

Once we are located in the route, we will modify the **index.html** file with a text editor.

We will replace the text string that appears between the **<title>** tags.

Example: **"<title>Uds<title/>**": We will replace the text string You with the text that we want to appear after the image.

Once the text has been modified, we must restart the Appliance UDS Server for the change to be applied.

NOTE: This modification must be carried out in all the UDS Servers that we have deployed.

UDS Enterprise Update

When we update the system, all the modifications made from the UDS Enterprise administration will be applied automatically, since they are saved within the UDS Enterprise Appliance Dbserver.

UDS ENTERPRISE, THE SOFTWARE VDI OF VIRTUAL CABLE

About UDS Enterprise

VIRTUAL CABLE

<u>UDS Enterprise</u> is a new software concept for creating a **fully customized virtualization** platform **for the workplace**. It provides **secure 24x7 access** from **any location and device** to all applications and software of an organization or educational center.

It allows you to combine Windows and Linux **desktop and application virtualization** in a single console, as well **as remote access** to Windows, Linux and macOS computers. Its Open Source base guarantees **compatibility with any third-party technology**. It can be deployed on premise, in a public, private, hybrid or **multicloud**. You can even combine several environments at the same time and perform automatic and **intelligent overflows** to optimize performance and efficiency. All with a **single subscription**.

About Virtual Cable

Virtual Cable is a company specialized in the digital **transformation of the workplace**. The company develops, supports and markets UDS Enterprise. It has recently been recognized as an **IDC Innovator in Virtual Client Computing** worldwide. Its team of experts has designed digital **workplace solutions** (VDI, vApp and remote access to physical computers) tailored to each sector to provide a unique user experience fully adapted to the needs of each user profile. Virtual Cable professionals have **more than 30 years** of experience in IT and software development and more than 15 years in virtualization technologies. **Everyday millions of Windows and Linux virtual desktops** are deployed with UDS Enterprise around the world.